

SubDevice.DeleteChannel

Delete a driver channel

Синтаксис

SubDevice.DeleteChannel(Name)

Название	Пример	Описание
Name	"Channel 1"	type: string channel name
На выходе		
Boolean		type: Boolean Success rate

Пример

```
var l_oDevice = module.GetDevice("MyDevice"); //Getting a device
var l_oSubDevice = module.AddSubDevice("SubDevice 1", l_oDevice); //creating
a subdevice
l_oSubDevice.AddChannel("Channel 1", [0x00, 0x00, 0x00, 0x00, 0x00, 0x00,
0x00, 0x00]);
l_oSubDevice.DeleteChannel("Channel 1"); //Deleting a channel
```