

```
//Creating an action with IR.ADVANCED_SLIDER and IR.ADVANCED_STRING
l_oSubDevice.AddAction("Set temperature", true, function(in_data){

var l_oData= JSON.Parse(in_data); //парсим объект IR.Log(l_oData.Temperature); //"35" - if a user
chooses 35 IR.Log(l_oData.Message); //"Hello, world!" - If a user entered this text

}, undefined, null, null, [{ Type: IR.ADVANCED_SLIDER, Name "Temperature", Min: 1 Max: 100 }, {
Type: IR.ADVANCED_STRING, Name "Message", Default: "Hello", Keyboard:
IR.KEYBOARD_DECIMALPAD}], false);
```