

```
//Creating an action with IR.ADVANCED_SLIDER and IR.ADVANCED_STRING var l_oAction =  
l_oSubDevice.AddAction("Set temperature", true, function(in_data){  
  
var l_oData = JSON.Parse(in_data); //парсим обьект IR.Log(l_oData.Temperature); //"35" - if a user  
chooses 35 IR.Log(l_oData.Message); //"Hello, world!" - if a user enters this text  
  
}, undefined, null, null, [{ Type: IR.ADVANCED_SLIDER, Name "Temperature", Min: 1, Max: 100 },  
{ Type: IR.ADVANCED_STRING, Name "Message", Default: "Hello", Keyboard:  
IR.KEYBOARD_DECIMALPAD }], false);
```